

Hitachi HH0-210 Exam

HH0-210: HDS Certified Implmenter-Enterprise

Practice Exam: HH0-210 Exams

Exam Number/Code: HH0-210

Exam Name: HDS Certified Implmenter-Enterprise

Questions and Answers: 104 Q&As

(Hitachi Data Systems)



We provide professional Hitachi HH0-210 exam information and free demo for HH0-210 certification exam's PDF. It is the best and the latest Hitachi Practice Exams. Download our HH0-210 PDF. We are committed to your ongoing success. Free PassBible HH0-210 exam and HH0-210 Q&As are constantly being updated and compared to industry standards. Exam : [HH0-210](#)

PassBible Test tool's advantages:

High Quality and Value of HH0-210 exam

PassBible Hitachi Hitachi Data Systems HH0-210 Practice Questions is developed and finished by Hitachi technical team , cover every field of the exam . Besides, we have verified HH0-210 answers,almost 100% correct.

100% Guarantee to Pass HH0-210 Exam

We promise to give you FULL REFUND if you fail the Hitachi Data Systems HH0-210 certification(Hitachi Certified Network Associate) with the use of our PassBible testing engine.

HH0-210 Self Test Mode

PassBible provides a simulated and interactive environment where you can test your knowledge and skills about HH0-210 to ensure enough assurance in real testing center.

Periodic Updates of PassBible HH0-210

Once there is some change on Hitachi HH0-210 exam, we will update it timely, and the product you buy will be updated within 90 days for free.

Professional and Efficient Service

We offer 7*24 customer support via diverse channels: LIVE CHAT,MAIL.Expecting the communication with you about IT certification.

This HH0-210 pdf demo do not include the questions and answers's picture.

Exam : Hitachi HH0-210

Title : HDS Certified Implmenter - Enterprise

1. You have created a Storage Device List and some User Accounts within Storage Navigator. The SVP has since failed and must be replaced.

How can you create a backup of this information so it can be easily restored after the failed SVP is replaced?

- A. Restore the ghost image available on the SVP.
- B. Use HiSat to keep track of the information in a CSV format.
- C. Ask the customer engineer to copy the source files from the SVP.
- D. Use the download configuration function of the Storage Navigator control panel.

Answer: D

2. Which ShadowImage operation is permitted when using Storage Navigator?

- A. Manage pairs and manage consistency groups
- B. Manage pairs but not manage consistency groups
- C. Manage pairs only within consistency groups
- D. Manage pairs in journal groups

Answer: B

3. Which three factors must be considered when planning a Non-stop SCSI microcode exchange on a Universal Storage Platform V? (Choose three.)

- A. Force production host data paths to failover to the alternate cluster.
- B. Schedule a time when the I/O workload is low.
- C. Confirm that all LUNs, external storage, and remote replication links have multiple paths across both clusters.
- D. Save the contents of the shared memory to the SVP hard disk.
- E. Ensure that the microprocessors are less than 50 percent busy.

Answer: BCE

4. You install a temporary license for a specific feature.

How long is the feature available on a Hitachi Enterprise storage system?

- A. 45 days
- B. 90 days
- C. 120 days
- D. 180 days

Answer: C

5. When is a microcode exchange process complete on a Hitachi Universal Storage Platform V?

- A. When the message "An exchange of a microprogram finished" is displayed.
- B. When all I/O resumes across all the mapped storage paths.
- C. Once the SVP has rebooted.
- D. When all the microprocessors flash memory update is complete.

Answer: D

6. To which two LANs must the SVP of a Hitachi Universal Storage Platform V be attached? (Choose two.)

- A. customer's intranet
- B. USP V internal LAN
- C. HiTrack dedicated user port
- D. secure management LAN

Answer: BD

7. A customer is using a Hitachi Enterprise storage system with clustered servers in an active/passive relationship. What must be done in Hitachi Dynamic Link Manager (HDLM) to ensure that the status of inactive paths on both passive and active nodes is monitored regularly?

- A. Switch on Auto failback.
- B. Setup intermittent Error Monitoring.
- C. Switch on Path Health Check.
- D. Set the reservation level to 2.

Answer: C

8. What is the purpose of the System Assurance Document?

- A. to ensure accurate and complete record of pre-installation data
- B. to guarantee that HDS equipment is insured during transportation
- C. to inform a channel partner that equipment is available for shipment
- D. to validate configuration changes for customers with a premium service contract

Answer: A

9. Which two topology settings should be used when connecting a Hitachi Universal Storage Platform V to a SAN switch? (Choose two.)

- A. Public Loop
- B. Private Loop
- C. Point-to-Point
- D. Fabric

Answer: CD

10. After completing a Hitachi Universal Storage Platform V installation or before upgrading the microcode, which tool must you use to ensure that the SVP can communicate with all components of the system?

- A. ping
- B. traceroute
- C. a network sniffer
- D. diags LAN TEST

Answer: D

11. Which two activities can be performed without interrupting user access to data in a Hitachi Enterprise storage system? (Choose two.)

- A. Upgrade Cache Memory from 32GB to 64GB.
- B. Run the CUDG4 (Control Unit DiaGnosis) test.
- C. Change the DKC system emulation type.
- D. Change a 2Gbps Fibre Channel feature to a 4Gbps Fibre Channel feature.

Answer: AD

12. Which three microcode exchange procedure modes are available in a Hitachi Enterprise storage system? (Choose three.)

- A. Alternate SCSI path
- B. Non-Stop SCSI host
- C. Postponed SCSI path
- D. Skip SCSI microprocessor
- E. Skip SCSI channel adapter

Answer: ABE

13. A TrueCopy project has the following requirements: Copy from site_A (Host_A) to site_B (Host_B).

You have defined two instances (horcm0.conf and horcm1.conf) for the application and one Command Device (CMD_A on site_A and CMD_B on site_B.)

What are two valid combinations of distributing the instances and defining access to the Command Devices on the different sites? (Choose two.)

- A. Host_A has access to CMD_A and CMD_B and runs horcm0.conf and horcm1.conf.
- B. Host_A has access to CMD_A and runs horcm0.conf. Host_B has access to CMD_A and runs horcm1.conf.
- C. Host_A has access to CMD_A and runs horcm0.conf. Host_B has access to CMD_B and runs horcm1.conf.
- D. Host_A has access to CMD_B and runs horcm0.conf. Host_B has access to CMD_B and runs horcm1.conf.

Answer: AC

14. You are connecting a Hitachi AMS2000 Family (AMS) system as external storage behind a Hitachi Universal Storage Platform V. You are using one path to each controller on the AMS2000 system.

Which statement describes how to complete the configuration?

- A. Enable intermittent error monitoring for both paths.
- B. Set path mode to "Multi".
- C. No special setting is needed.
- D. Set the primary path to point to the AMS default controller.

Answer: C

15. You are enabling the Syslog transfer in Storage Navigator to send the Syslog output to the primary Syslog server. Which two additional settings must be made to allow the transfer? (Choose two.)

- A. the primary server subnet settings
- B. the IP address of the primary server
- C. the Syslog file format
- D. the port number for the primary server

Answer: BD

16. Which three statements describe the Service Processor (SVP) of the Hitachi Universal Storage Platform VM? (Choose three.)

- A. The SVP does have a display and keyboard.
- B. The SVP has access to user data stored on the system.
- C. Connecting the SVP with a service center enables remote maintenance of the system.
- D. The SVP collects performance data for all key components of the system.
- E. The SVP enables the service representative to configure, maintain and upgrade the system.

Answer: CDE

17. You are installing a new Hitachi Universal Storage Platform V system and need to exchange the short wave SFP transceivers with the long wave type.

To perform the exchange, which two actions are required? (Choose two.)

- A. Confirm successful replacement by checking that SFP indicators have changed from blue to green on the Storage Navigator main screen.
- B. Run the SFP exchange wizard.
- C. Set SFP mode on the SVP.
- D. Confirm successful replacement by checking 'SFP kind' information on the maintenance screen.

Answer: CD

18. You need to enable Copy-on-Write SnapShot software on a Hitachi Universal Storage Platform VM.

Which two are required? (Choose two.)

- A. remote replication license
- B. ShadowImage license
- C. additional cache memory
- D. additional shared memory

Answer: BD

19. What information is displayed on the Information tab page of Storage Navigator? (Choose two.)

- A. the device view of the connected system
- B. the product name of the connected system
- C. the information for the root user of the connected device
- D. the microcode version of the storage system

Answer: BD

20. Which two steps must be taken when performing a microcode exchange on a Hitachi Universal Storage Platform VM? (Choose two.)

- A. Disconnect the SVP from the customer LAN.
- B. Confirm that all components are at the correct starting code level.
- C. Update SVP microcode last.
- D. Resolve all SIMS before beginning a microcode exchange.

Answer: BD

Related Hitachi HH0-210 Exams

<u>hh0-120</u>	<i>Hitachi Data Systems Storage Foundations - Modular Exam</i>
<u>hh0-110</u>	<i>Hitachi Data Systems Storage Foundations - Enterprise Exam</i>
<u>HH0-210</u>	<i>HDS Certified Implmenter-Enterprise</i>
<u>HH0-220</u>	<i>HDS Certified Implmenter-Modular</i>
<u>HH0-400</u>	<i>Hitachi Data Systems Architect-Business Continuity</i>
<u>HH0-280</u>	<i>HDS Implemetation Specialist - Storage Management</i>
<u>HH0-440</u>	<i>Storage Architect - Performance & Virtualization</i>
<u>HH0-270</u>	<i>HDS Implmenetation Specialist-Business Continuity Exam</i>
<u>HH0-330</u>	<i>HDS Storage Manager-Business Continuity Enterprise</i>
<u>HH0-380</u>	<i>Hitachi Data Systems Architect - Business Continuity</i>
<u>HH0-340</u>	<i>Hitachi Data Systems Storage Manager-Storage Management</i>
<u>HH0-015</u>	<i>TagmaStore NSC-Installation and Configuration</i>
<u>HH0-005</u>	<i>TagmaStore AMS and WMS-Installation and Configration</i>
<u>HH0-240</u>	<i>HDS Storage Manager-Business Continuity Modular</i>
<u>hh0-200</u>	<i>certified modular integration specialist exam</i>
<u>HH0-230</u>	<i>HDS Storage Manager-Business Continuity Enterprise</i>
<u>HH0-020</u>	<i>Adaptable Modular Storage 2000 Family Install and Config</i>
<u>HH0-250</u>	<i>Hitachi Data Systems Implementer File Services-NAS</i>

Other Hitachi Exams

<u>hh0-200</u>	<u>hh0-120</u>	<u>HH0-380</u>	<u>HH0-220</u>	<u>HH0-005</u>	<u>HH0-340</u>	<u>HH0-240</u>	<u>HH0-280</u>
<u>hh0-110</u>	<u>HH0-230</u>	<u>HH0-250</u>	<u>HH0-440</u>	<u>HH0-210</u>	<u>HH0-400</u>	<u>HH0-015</u>	<u>HH0-020</u>
<u>HH0-270</u>	<u>HH0-330</u>						